OnTime

Powered by ClockedIn

SmartHub Radius Setting





SmartHub Radius Settings

Purpose

The radius setting allows the registered user to clock in and out of multiple devices within a radius of the registered device.



Key points

- If set to 0, the user can only clock in and out of the registered device.
- Default is 5 miles.





 An "All locations" option is available. This will distribute the registration to every device, allowing the user to clock in / out on all devices. This has been designed for admin and super admin users but can also be used for employees if required.

Methods of using and changing the radius

OnTime

After the finger registration process (this can be skipped if not using fingerprints), the next screen will give the option of entering a pin. On this screen you can change the radius number.

ADMIN PAGE									
	C10009 Jon H								
New / Edit User Registration	Pin Registration								
Jon									
н	Set location Radius 5 Miles								
C10009	All Locations								
	Register FOB								
	REGISTRATION COMPLETE								
Please scan QR Code for instructional video on Finger Scan registrations									
Click here to go back	View Employee Online								

In the event of a user <u>re-registration</u> (a user who has been registered previously, but now going through the process again), the radius setting will be centred from that new device (if registering on a different device to the original).

AirStack

The radius can be changed within employees tab of AirStack (this feature requires AirStack v4.0 or higher).

Search the employee's name or employee number using the search box. When you have found the relevant employee, click on the pen icon within the radius column







AirStack admin@clockedin.com							m 🔁 Log Ou					
Report	✓ Admin Setting ▼	Message 🔻	U	pload Logo	Upload AP	K Add Email	Device 🔻	Employees	Location	Sync HR Employees	Manag	e Admin
rStack > Empl	oyees											
ind by Status Registered		~	Search Jon				/ Unique Identifier se Select		↓ Sea	Irch Export Excel		
Employee											Show	/ 20 🗸 Entri
User Name 🔺	Email	Employee Number	PIN Number	Role	Unique Identifier	Registration Status	R	adius	Remove	SwipeAndGo	Employee Image	Action
Jon H	jon.house@cubepurple.com	C10009	1705	SuperAdmin	testA9 💉	Face Scan, Finger Scan, FOB, F	Pin Register		🖲 & 🕀 🔘		0	Update Role
						Page 1 of 1						
Image: First Image: Previous P1 Next Last												
wipeAndGo Las otal User Regist otal User Un-reg	ast month: 11 month: 1280/1280 .t Month: 2 ered: 43			Fo		on how to use the AirStack / O ht © Clockedin Limited, Uppingham		meclocks.uk		н	R Version: 11_3_2	AS Versic 042_112_CLOCKAS Trus Compar





This allows you to change the radius number or set to all locations.

Radius		×
Radius	Is All Location	
		Save Close

You can also change the centre of the radius by changing the device within the unique Identifier column. Click on the pen within the unique identifier column and select the new device you want the user to be registered to. This is useful in the event of an employee permanently moving locations.







						DevAir				admin@clockedin.com			
Report	- Admin Setting -	Message 🔻	Up	load Logo	Upload APK	Add Email	Device -	Employees	Location	Sync HR Employees	Manag	ge Admin	
rStack > Emplo	oyees												
Find by Status		~	Search Jon				nd by Unique Identif Please Select	fier	✓ Se	earch Export Excel			
Employee											Shov	v 20 🗸 Entr	
User Name 🔺	Email	Employee Number	PIN Number	Role	Unique Identifier	Registration Sta	atus	Radius	Remove	SwipeAndGo	Employee Image	Action	
Jon H	jon.house@cubepurple.com	C10009	1705	SuperAdmin	testA9 💉	Face Scan, Finger Scan, Fo	OB, Pin Register	5 💉	())) ()) ()) ()) ()) ()) ()) ()) ()) ()		Ø	Update Ro	
						Page 1 (st ₩					
wipeAndGo Las otal User Regist otal User Un-reg	ast month: 11 month: 1280/1280 at Month: 2 tered: 43			For		on how to use the AirStac t © Clockedin Limited, Upping				ŀ	R Version: 11_3_2	AS Versi 042_112_CLOCKA Tru Compa	





Update Employee Unique Identifier								
	testA9 -]						
			Submit					